

LinkRunner® 10G v2.2 Release Notes

May 9, 2023

These LinkRunner 10G Release Notes briefly describe the new features and enhancements included in the release.

[See software upgrade Instructions at the end of this document](#)

Version 2.2 New Features

All apply to both LinkRunner 10G 100 and 200 models unless noted.

Local Storage Management:

- User Manuals are now stored on www.netally.com instead of local storage (click Guides on the home screen to access).

Performance App Improvements:

- Performance app test settings are now included with the test results sent to and displayed in Link-Live.


Internal Temperature Monitoring:

- Enhancements to internal temperature monitoring designed to protect the unit in abnormal conditions such as obstructed air vents or ambient temperatures above 45C / 113F.

Upgrading to Version 2.2

If you have claimed your unit to Link-Live.com, we highly recommend following the Over the Air (OTA) Firmware Update procedure:

1. To check for available software updates at any time, open the Link-Live App from the Home screen.
2. In the Link-Live App, touch the menu icon or swipe right to open the left-side Navigation Drawer.



3. Touch **Software Update**. The Software Update screen opens and displays the version number of any available updates.
4. Touch **Download + Install** to update the System.
5. When finished, the unit will restart.

Thank you for your investment in NetAlly products!

This software update is a key benefit of your AllyCare™ Premium Support Services contract. For more information about AllyCare benefits, see [AllyCare Support · Customer Self-Service \(netally.com\)](https://netally.com/customer-self-service)